

Veo+ Public Manifest

March 27, 2019

2019-03-28 Veo+ 4.2.3

New Features

None, follows other products' software version ID.

2019-03-12 Veo+ 4.2.2

New Features

3653 Low profile X0AW wedge dimensions update

Fixed Issues

3655 Crash correction in the sensitivity wizard (mono scan)

2018-11-22 Veo+ 4.2.1

New Features

3182 Add WP2 New Encoder Configuration File (update Tick/s)

3420 Correction of the Focal distance offset for DLA configuration

3615 New Layout implementation (4 PA-2 TOFD)

3641 Include now Starc and TStarc UT probe file in the internal database

3642 New ezDGS Karl Deutsch Probes added in internal database

3250 Update D1S Probes Models

3254 Width dimensions up to date on D1A wedge series

2018-10-17 Veo+ 4.2.0

New Features

None, follows other products' software version ID.

2018-04-26 Veo+ 4.1.0

New Features

2454 Linear Scan elements resolution can now be set by user

2727 New FMC-TFM software option for VEO+

3127 New option to synchronize gate with the previous one

3135 Updated Translation for all languages

3157 New option to hide gates ID information in the A-Scan view

3162 Updated Help Files

3185 Increase probe number limitations for multiscan configuration

3188 New option to ask to save configuration file before going to record mode

3193 Tabs and icons look & feel update

Fixed Issues

3125 Fix possibility to set thickness at less than 2mm for sectorial scan

2018-02-16 Veo+ 3.19.4

New Features

None, follows other products' software version ID.

2018-02-16 Veo+ 3.19.3

New Features

None, follows other products' software version ID.

2018-02-01 Veo+ 3.19.2

New Features

116 Updated phased array probes and wedges database

Known Issues

585 Issues when zooming on views with keyboard

708 Issues converting TCG to DAC with angulated wedge

870 Part Overlay not in correct position when B-Scan orientation is change

2017-12-16 Veo+ 3.19.1

New Features

061 Updated phased array probes and wedges database

Known Issues

585 Issues when zooming on views with keyboard

708 Issues converting TCG to DAC with angulated wedge

870 Part Overlay not in correct position when B-Scan orientation is change

2017-11-24 Veo+ 3.19.0

New Features

None

Fixed Issues

980 Fix potential issue in hardware boot sequence causing noise on UT channels

Known Issues

585 Issues when zooming on views with keyboard

708 Issues converting TCG to DAC with angulated wedge

870 Part Overlay not in correct position when B-Scan orientation is change

2017-09-27 Veo+ 3.18.12

New Features

792 New PCS parameter is editable in play mode when using TOFD scan

869 New Czech is now a supported language

930 UT wedge & probe database update

934 New X0 low profile probes and wedges series has been added to the database

Fixed Issues

448 Windows requests to scan USB after every use with instrument

789 Fix Cartesian cursor not showing true depth measurement in certain views

806 Fix media browser not moving files properly

Known Issues

585 Issues when zooming on views with keyboard

708 Issues converting TCG to DAC with angulated wedge

870 Part Overlay not in correct position when B-Scan orientation is change

2017-05-05 Veo+ 3.17.11

New Features

378 Configuration Report according to ASME/API/AWS standards

691 Optimized features for Pitch & Catch configuration with Phased Array

701 New Reload TCG/DAC curve feature when breaking calibration

751 New Option to hide documentation for training purposes

Fixed Issues

512 System asked to save file when pressing shutdown button

740 Compatibility issues with files created in version 3.8.2 or earlier

799 Fix SDH wedge delay wizard on sectorial scan

801 Cursors info missing from expanded reports

Known Issues

585 Issues when zooming on views with keyboard

708 Issues converting TCG to DAC with angulated wedge

2017-04-20 Veo+ 3.16.2

New Features

738 New Automatic Reset of Scan Axis for Circular parts

758 New Scrolling Merged C-scan in encoded view

Fixed Issues

744 Fix High Resolution problems on long scan axis

Known Issues

448 Windows requests to scan USB after every use with instrument

585 Issues when zooming on views with keyboard

708 Issues converting TCG to DAC with angulated wedge

2017-03-21 Veo+ 3.15.4

New Features

735 Updated Translation for all languages

434 New Scrolling C-scan in encoded view

045 New Cloud Remote access solutions powered by LogMeIn Hamachi

Fixed Issues

749 Add BIOS programming support for new veo+ COM modules

586 Fix overlapped tabs when using Japanese language

029 Cartesian cursor not showing true depth measurement

199 Data is not erased when using invert scan direction

489 DGS curve disappearing on load configuration

592 Crash on save view data to .csv

640 Crash on load .utdata file with Russian language activated

Known Issues

448 Windows requests to scan USB after every use with instrument

585 Issues when zooming on views with keyboard

740 Compatibility issues with files created in version 3.8.2 or earlier

2017-01-26 Veo+ 3.14.3

New Features

2272 Prod Tools & Service Centers Improvements

568 Improved WiFi functionalities

Fixed Issues

2294 TCG Calibration breaking when dB ref is changed

2604 System switches from russian to english at reboot

601 After Reboot, WiFi password is not recognized

616 Cannot rename folder after moving/copying file into it

1704 Rescue process to factory default cannot be completed properly

1883 Element activation wizard for a scan cancels calibration of other scans

2016-10-25 Veo+ 3.13.3

New Features

None

Fixed Issues

2165 TOFD Gate measurements improvement

Known Issues

32 File loaded from USB key cannot be saved after removing the key

40 Maximizing Merged C-scan view during acquisition clears the view

635 WiFi refresh button in configuration screen not working. - WA turn OFF/ON the antenna

363 Wheel touch doesn't work while in velocity wizard - WA use arrows

236 In some occasion a split DAC vertical lines is not drawn - WA re-implement the DAC

231 Redundant info in 3D view or wrong abbreviation used for focal distance

2016-09-16 Veo+ 3.12.7

New Features

1575 New automatic filenaming functionality

1697 New ezDGS functionalities: curve importation from GE probe (single & twin crystal probes)

1569 New PA natural focal mode (no-focusing)

1715 New default FTP user name = ftpuser

1716 New default VNC password = password

2005 New UI language update: Japanese + updates on other languages

1922 Preferred recording drive is SSD for fast record of large files

1952 Integrated wedge is now part of the wedge advanced parameters (yes/no)

2087 DAC to TCG is now available in SCAN menu (stop mode)

Fixed Issues

- 263 Reset all in Time-based should reset all data
- 601 WiFi right password isn't recognize correctly after reboot
- 406 Cross Hair Cursor doesn't move in S-Scan when moving the Mouse Cursor
- 642 Change the default value for Elmt Diameter of a mono circular probe
- 779 Overlapped UI tabs in Hungarian, German, Japanese, Slovak
- 1838 Change weld on curved surface with constant path focus breaks calibs
- 2025 We not supposed change dB during recording
- 2079 TCG curve cannot be edited after modifying the gain
- 2081 Error when adding a second scan on curved surface

Known Issues

- 32 File loaded from USB key cannot be saved after removing the key
- 40 Maximizing Merged C-scan view during acquisition clears the view
- 635 WiFi refresh button in configuration screen not working. - WA turn OFF/ON the antenna
- 363 Wheel touch doesn't work while in velocity wizard - WA use arrows
- 236 In some occasion a split DAC vertical lines is not drawn - WA re-implement the DAC
- 231 Redundant info in 3D view or wrong abbreviation used for focal distance

2016-06-22 Veo+ 3.11.6

New Features

- 178 New software option for PA-CSC
- 440 New example files for PA-CSC
- 1671 New UTDATA, UTCFG, PDF, IMAGE icons
- 1543 Auto TCG sweep with skips
- 701 Add WiFi IP adress in About Windows
- 1799 New layout implementation
- 579 Now default weld angle value is 30° (used to be 45°)
- 1416 Wedge PA angle auto-calibration wizard
- 1448 Review of calibration breakers relations
- 57 If USB unplug it now deletes recent files link
- 1627 Change Radius for Diameter
- 1684 Add IFT culling option in the beginning of TCG/DAC Wizard
- 1738 Replace "New Inspection Wizard" by "Create New Configuration"

Fixed Issues

- 638** Code doesn't accept mono refracted at angle 90°
- 1798** Cross Hair cursor doesn't show the measurement at its intersection in many views
- 322** F3 reset shortcut doesn't work when 2D quadrature encoded and Timed Base
- 609** Screen brightness parameter missing for Veo's
- 629** DGS Wizard Ends too fast
- 1615** Welcome screen - battery indicators are cut off
- 1439** AQR indicator mis-behavior with 2 TOFD scans
- 1630** Going back in wizard replaces value to default

Known Issues

- 32** File loaded from USB key cannot be saved after removing the key.
- 40** Maximizing Merged C-scan view clears the view.
- 565** 3D views improvement for P&C functionalities.
- 635** WiFi refresh button in configuration screen not working. - WA turn OFF/ON the antenna.
- 601** WiFi right password isn't recognize correctly after reboot - WA re-enter password.
- 363** Wheel touch doesn't work while in velocity wizard - WA use arrows
- 280** Measures in Part References don't consider Encoding Area offset+rotation
- 263** Reset all in Time-based should reset all data - WA make a manual reset
- 236** Sometimes split DAC vertical lines are not drawn
- 231** Redundant info in 3D view or wrong abbreviation used for focal distance
- 406** Cross Hair Cursor doesn't move in S-Scan when moving the Mouse Cursor

2016-05-02 Veo+ 3.10.11

New Features

None

Fixed Issues

- 90** Error in FL calculation - Beam exit point outside wedge

2016-04-21 Veo+ Release 3.10.10

New Features

- 1476** Update for multiple OS security fixes.
- 1584** New layout for 5 Scan that includes a B-Scan.

Fixed Issues

- 1397** Mono DAC interface.
- 1490** UT function noise.

2016-03-15 Veo+ 3.10.8

First public release.

Known Issues

- 32** File loaded from USB key cannot be saved after removing the key.
- 40** Maximizing Merged C-scan view clears the view.
- 565** 3D views improvement for P&C functionalities.
- 609** Screen brightness parameter missing.
- 635** WiFi refresh button in configuration screen not working. - WA turn OFF/ON the antenna.
- 601** WiFi right password isn't recognize correctly after reboot - WA re-enter password.
- 592** Auto FSH in DGS wizard not accurate - WA make manual adjustment.
- 363** Wheel touch doesn't work while in velocity wizard - WA use arrows.
- 322** F3 reset shortcut doesn't work when 2D quadrature encoded - WA manual reset.
- 280** Measures in Part References don't consider Encoding Area offset+rotation.
- 263** Reset all in Time-based should reset all data - WA manual reset.
- 236** Sometimes split DAC vertical lines are not drawn.
- 231** Redundant info in 3D view or wrong abbreviation used for focal distance.
- 1439** AQR indicator unsuspected behavior when having 2 TOFD scans.
- 1541** Part Thickness and geometry index offset breaks calibration